

TopGear V2.45 EA Manual

This EA Works Based on the Price Channel Stop V1.3 Indicator. The price Channel stop Indicator is similar to Moving averages, but here it calculates the **Risk % (Percentage)**.

- **Indicator Channel Period:** Number [N] of candles to check the average price

Formula:

- **Upper Channel** = High [N] - (High [N] - Low [N]) * Risk
 - **Lower Channel** = Low [N] + (High [N] - Low [N]) * Risk
- **Risk:** Percentage %
Example: 30% risk = **0.3**

EA Functions:

EA Buid with 2 Sets of Price channel stop indicator **Main Trend** & **Internal Trend** Finder.

Main Trend: High Timeframe channel period (Example: 21-period channel) is to check over the trend in applied chart/currency.

Variable	Value
ab 00000000	-- Main Indicator Settings --
123 Lots	0.01
123 Slippage	30
ab Indicator_file	pricechannel_stop_v1.3
123 Indicator_Period	current
123 ChannelPeriod	21.0
123 Risk	0.3
123 MaxTrade	10

- **Indicator_file:** Price Channel Stop indicator file name (can only support Updated Versions of Price Channel Stop indicator).
- **Indicator_Period:** Price Channel Stop indicator Timeframe - can select higher timeframes for better or higher timeframe trends
- **Channel Period:** Indicator Period.
- **Risk:** Indicator Risk
- **MaxTrade:** Max open trades for the current cycle.

Internal Trend: Lower the time frame channel period (Example: 09-period channel) to open multiple trades in the same trend.

-- 2nd Indicator Settings --	
Active_EA2	true
Indicator_Period2	current
ChannelPeriod2	9.0
EASignalType	TrendSignal

- **Activate_EA2:** Enable or Disable the 2nd/inter-trend indicator.
- **Channel Period:** Indicator Period.
- **Risk:** Indicator Risk
- **EASignalType:** 2nd EA trade opening conditions based on indicator signal, this function **only opens trade based on the Main trend direction.**
 - **TrendSignal:** Open trade when **Main Trend and Internal Trend are in the same direction.**
Example: **Buy signal** (Main Trend [**UP Trend**] & Internal [**UP Trend**]).
 - **ReversSignal:** Open trade when the **Internal Trend is down.**
Example: **Buy signal** (Main Trend [**UP Trend**] & Internal [**Down Trend**]).
 - **Both:** Open trade when the **2nd indicator gives a signal.**
Example: **Buy signal** (Main Trend [**UP Trend**] & Internal [**UP Trend** or **Down Trend**]).

Takeprofit & stoploss:

-- Stoploss & TP Settings --	
Stoploss	No_Stoploss
StopLoss_pip	200
StopLoss_Bars	5
UseProfit Trail	true
TrailingStop	200
Use TakeProfit	false
TakeProfit	100

- **Stoploss:** Stoploss can be selected to multiple functions.
 - **No_Stoploss:** Without stoploss EA will open trades.
 - **Fixed_Stoploss:** **Stoploss_pip** Fixed pips of Stoploss value input.
 - **Prev_No_Bars:** **Stoploss_Bars** Previous Number Bars High/Low as stoploss.
 - **Channel_Stop:** Main Indicator Price channel value as Stoploss.

- **UseProfitTrail:** Enable or Disable Trailing stoploss, **TrailingStop** value.
- **UseTakeProfit:** Enable or Disable TakeProfit, **Takeprofit** value.

Revers Trend Exit Orders: Enable or Disable function

ab	000000	-- Time Filter --
Time_Filter		false
ab	start_Time	00:00
ab	end_Time	23:59
Order_close_Revers_signal		true

When Main trend Indicator change Trend signal EA will close exits all open trade, by previous trend.

Time Filter:

Time filter for activate EA is specific timezone.

- **Time_Filter:** Enable or Disable.
- Start_time: EA Activation time.
- End _time: EA Disable time period or end time of trading